

## Hardware programming info for the Atari Portfolio Smart Parallel Interface (HPC-101)

## Hardware ports

Four ports are used to communicate with the 82C55 UART used in Portfolio's smart parallel interface. There is a control register (port/memory address \$807B) and 3 I/O ports (Port A - address \$8078, Port B - address \$8079 and Port C - address \$807A), which can be individually configured as inputs or outputs (Port C even individually for the higher and lower nibble). The ports are exposed to the DB-25 connector as shown in the following diagram





PINS MARKED WITH AN "X" ARE NOT EXPOSED VIA THE SMART PARALLEL INTERFACE

Not all ports are fully exposed to the DB-25. Ports B and C have various signals which are not available. These appear to be connected to ground at the DB-25 port. The following table shows the available signals arranged by ports/bits

	Port A		Port B		Port C	
Bit	Pin#	Signal	Pin#	Signal	Pin#	Signal
0	2	D0	1	Strobe	12	Paper
1	3	D1	14	Autofeed	13	Select
2	4	D2	16	Init/Reset	-	-
3	5	D3	17	Select In	15	Errors
4	6	D4	-	-	11	Busy
5	7	D5	-	-	10	Ack
6	8	D6	-	-	-	-
7	9	D7	-	-	-	-

## Port control

The control register (807B) determines how the individual ports are switched (inputs vs outputs). The following table outlines the configuration options for each port and the associated value to be written to the control register for each option

By default (printer control mode), the control register contains the value **138 (089h)** - Ports A and B set to output (data and control) and port C set to input (acknowledge, busy, error etc)

Control register port (\$807B)							
Value		Port directions					
Hex	Decimal	Port A	Port B	Port C (Io)	Port C (hi)		
0080	128	OUT	OUT	OUT	OUT		
0081	129	OUT	OUT	IN	OUT		
0082	130	OUT	IN	OUT	OUT		
0083	131	OUT	IN	IN	OUT		
0088	137	OUT	OUT	OUT	IN		
0089	138	OUT	OUT	IN	IN		
008A	139	OUT	IN	OUT	IN		
008B	140	OUT	IN	IN	IN		
0090	144	IN	OUT	OUT	OUT		
0091	145	IN	OUT	IN	OUT		
0092	146	IN	IN	OUT	OUT		
0093	147	IN	IN	IN	OUT		
0098	152	IN	OUT	OUT	IN		
0099	153	IN	OUT	IN	IN		

009A	154	IN	IN	OUT	IN
009B	155	IN	IN	IN	IN